

eque Quick Reference Guide (with Images): TalkBack 9.1+ for Android

Recommended browser: Chrome (Android OS 7.0 or higher), Firefox (Older versions of Android OS)

Getting Started

Enabling TalkBack: Go to Settings > Accessibility > TalkBack to turn on TalkBack. To activate the TalkBack shortcut, go to Settings > Accessibility and turn on the Volume Key Shortcut. You can then hold the volume keys for a few seconds to turn TalkBack on or off.

The TalkBack menu: contains commands that are relevant anywhere on your device. To open the TalkBack menu, swipe down then right, or swipe up then right. Or on devices with multi-finger gestures*, you can also do a three-finger tap.

Reading controls: allow adjustment of reading settings, such as being able to swipe to read by headings or by lines, and to change the speech rate. To open the reading controls, swipe up then down, or down then up. Or on devices with multi-finger gestures*, you can also do a three-finger swipe left or right, or up or down. Repeat the same gesture to cycle through the different reading controls.

Note: Some menu options and reading controls are hidden by default. Go to TalkBack Settings > "Customize menus" to choose which





1. Select the desired reading control 2. Swipe down

Swipe right





Swipe right or left Or explore by touch



Double tap

menu and select "Search screen") to search for the desired section



1. Select the desired reading control 2. Swipe up



Go to home screen Swipe up, then left

Recent apps Swipe left, then up

Notifications Swipe right, then down **Or** two-finger swipe

down from top

Start or stop media **Or** Answer or end a call Two-finger double tap

Reading Text

Say prior paragraph, line, word, character



1. Select the desired reading control 2. Swipe up



1. Open TalkBack menu 2. Select "Read from next item" **Or** two-finger triple tap



1. Open TalkBack menu 2. Select "TalkBack Settings" > "Verbosity" > "Speak phonetic letters"



1. Select the desired reading control 2. Swipe down



1. Navigate by words 2. Open TalkBack menu 3. Select "Spell last spoken phrase"

Tables



Swipe right



Swipe left



Explore by touch



Note: TalkBack reads table cells in order left to right, starting at the top row.

Forms

Select and deselect checkboxes



Double tap

Open combo box (<select>)



Double tap

Browse combo box options



Explore by touch Or swipe right or left

Select multiple combo box



Double tap each option to select or deselect

Toggle radio button selection



1. Swipe right or left to the desired option

2. Double tap to select

Other Commands

Adjust a slider up or right



Or swipe up

Pass-through next gesture to



Four-finger double tap and hold (on devices with multifinger gestures*)

Adjust a slider down or left



Swipe left, then right Or swipe down

Voice commands



1. Swipe right then up. 2. Listen for a confirmation sound.

3. Speak a command. (Available only with TalkBack 9.1 and up.) Search for a word or phrase



Swipe left, then down.

Typing: When in a text editing field, a virtual keyboard appears at bottom of screen. Drag finger over letters, and release when vou hear the desired letter.

Speak characters typed: In TalkBack Settings, enable "Keyboard echo."

Gesture hints: Select "TalkBack Settings" > "Verbosity" > "Speak usage hints."

Note: TalkBack varies depending on the version of Android and the web browser in use. Some options may be unavailable.

Reformat documents for simpler viewing:

Chrome: Go to Chrome settings > Accessibility > select "Simplified view for web pages." A button for simplified view will appear at the bottom of the screen, when supported.

Firefox: Reader View. When viewing an article, the button appears in the URL bar.

*Multi-finger gestures—gestures using three or more fingers simultaneously—are available only with TalkBack 9.1 and up, only on some Android devices, such as Google Pixel 3 and up, and some other brands' models like Samsung Galaxy.

Full list of commands: http://tinyurl.com/commands-talkback

